

Configuring FTP/HTTPS server

For HTTP(S) Connection

Installing Outlook To JIRA Connector HTTP(S) Configuration:

1. Login to JIRA using an Administrator account
2. Click on "Add-ons"
3. Navigate to the "Outlook To JIRA" section found in the left menu
4. Click on "AutoUpdate Configuration"
- 5- Select "Enable AutoUpdate"
- 6- Select AutoUpdate Method as "Via HTTP(S) Connection"

Outlook To JIRA Auto Update Configuration

Enable Auto Update

Note: Enabling auto update will allow end-users to automatically update to the latest OTJ. Check [documentation](#).

Via HTTP(S) Connection

HTTP(S) URL:

Via FTP Connection

FTP URL:

FTP UserName:

FTP Password:

Under the HTTP(S) tab

- 7- Infosysta HTTP(S) URL will be filled by default when "Default HTTP(S)" is clicked

If connecting to your own HTTP(S) URL you can insert your link and click on save

For FTP Connection

Installing Outlook To JIRA Connector FTP Configuration:

1. Login to JIRA using an Administrator account
2. Click on "Add-ons"
3. Navigate to the "Outlook To JIRA" section found in the left menu
4. Click on "AutoUpdate Configuration"

5. Check the "Enable AutoUpdate" checkbox
6. Choose "Via FTP Connection" method
7. Fill in the required field in the FTP Tab (By default, infosysta configuration is set)
 - a. **FTP URL:** This is the FTP server URL where your Outlook add-on will check for the latest version
 - b. **FTP Username:** The Username of the FTP administrator
 - c. **FTP Password:** The password of the FTP administrator



You can reset your FTP configuration to Infosysta's settings at any time by clicking on "Default FTP" button

8. Click on Save

Outlook To JIRA Auto Update Configuration

Enable Auto Update

Note: Enabling auto update will allow end-users to automatically update to the latest OTJ. Check [documentation](#).

Via HTTP(S) Connection

HTTP(S) URL:

Via FTP Connection

FTP URL:

FTP UserName:

FTP Password: